

SMTP服务器：发送邮件的邮箱的SMTP服务器, 可从邮箱提供商处获取

如：

网易 SMTP服务器 smtp.163.com

QQ邮箱 SMTP服务器 smtp.qq.com

腾讯企业邮箱 SMTP服务器 smtp.exmail.qq.com

新浪邮箱 SMTP服务器 smtp.sina.com

发送邮件配置

设置调用第三方smtp均需要对方开启smtp服务，设置正确若不能发送需要检查核实账号密码是否正确。

SMTP服务器 smtp.163.com

邮件地址：填写发送邮件的邮箱

用户名：填写登录邮箱的账号（一般就是邮箱地址）

密码：填写上面设置的授权码（注意：使用新浪邮箱时，密码为登录邮箱的密码!）

加密方式、端口：这里提供了两种加密方式，若确认填写的邮件配置无误，测试发件不成功时，可尝试更换一种方式及SSL端口

首页 / 系统 / 基础设置 / 全局设置 / 全局设置

全局设置

The screenshot shows a web interface for configuring email settings. On the left is a sidebar menu with items: 基本, 会员, 工单, 积分, 财务, 充值, 合同, 产品, 邮件 (highlighted), 短信, 接口, 安全, 上传, PUSH, 推广, 自动化. The main content area is titled '邮件' and contains a sub-section '邮箱设置'. The configuration fields are: SMTP服务器 (input field with help icon), 发件邮箱地址 (input field with help icon), 发件人显示名称 (input field with help icon), 发件邮箱密码 (input field with help icon), 注: 留空则不修改, 加密方式 (radio buttons for TLS (selected), SSL (?)), 邮箱SSL端口 (radio buttons for 25 (selected), 465, 其他 (?)), 测试收件箱 (input field with '测试发件' button and help icon). Below this is a '身份安全验证' section with a '管理员密码' (input field) and a '保存设置' (Save Settings) button.

开启SMTP服务

网易邮箱SMTP服务:

SMTP服务器地址[smtp.163.com

选择需要开通的SMTP服务

The screenshot shows the 'POP3/SMTP/IMAP' settings page in the 163.com email client. The page is divided into several sections:

- Left Sidebar:** Contains navigation links such as '常规设置', '邮箱密码修改', '签名/电子名片', '来信分类', '信纸', '手机号码邮箱', '帐号与邮箱中心', '邮箱安全设置', '邮箱手机服务', '反垃圾/黑白名单', 'POP3/SMTP/IMAP', '客户端授权密码', '文件夹和标签', '多标签窗口', '邮箱触点', '换肤', '实验室', and '升级VIP邮箱'.
- Main Content Area:**
 - POP3/SMTP/IMAP Section:** Features two checkboxes: 'POP3/SMTP服务' (unchecked) and 'IMAP/SMTP服务' (unchecked). A red box highlights the 'POP3/SMTP服务' checkbox with the text '勾选此处' (check here). Below these are a dropdown menu for '收取最近30天邮件' and a warning: '温馨提示: 请使用授权码登录第三方邮件客户端'.
 - Second POP3/SMTP/IMAP Section:** Features a checked checkbox '开启客户端删除邮件提醒' and a note: '当邮件客户端删除邮件时, 系统会通过邮件发送提醒信息'.
 - Buttons:** '保存' (Save) and '取消' (Cancel) buttons are located at the bottom of the main content area.
- Right Panel:** A dropdown menu is open, showing options: '常规设置', '邮箱密码修改', '帐号与邮箱中心', '邮箱安全设置', '手机服务', 'POP3/SMTP/IMAP', and '换肤'. A red box highlights the 'POP3/SMTP/IMAP' option.
- Bottom Section:** A '提示' (Notice) section lists server addresses: 'POP3服务器: pop.163.com', 'SMTP服务器: smtp.163.com' (highlighted with a red box and arrow), and 'IMAP服务器: imap.163.com'. It also lists '网易官方邮件客户端: 网易邮箱大师' and '其他邮件客户端: PC端设置帮助'.

开启服务



授权码

授权码是用于登录第三方邮件客户端的专用密码。

适用于登录以下服务: POP3/IMAP/SMTP/Exchange/CardDAV/CalDAV服务。

设置客户端授权码: 开启 **选择开启**

关闭 (默认)

启用时间	停用时间
2016-12-15 11:43:03	2016-12-15 12:38:17

启用授权码, 避免密码泄露造成邮箱安全隐患

设置客户端授权码

i 为了避免授权码设置可能造成的重要信息泄露, 需进行手机短信验证

手机号 134*** [免费获取短信验证码](#)

验证码

[手机换号了, 无法验证?](#)

设置授权码

安全隐患, 使用邮件客户端更安心。 [了解更多 >>](#)

设置授权码

为了您的邮箱安全, 请设置授权码。
登录第三方邮件客户端时, 请在密码框输入本授权码。

输入授权码:

确认授权码:

成功:



QQ邮箱SMTP服务

SMTP服务器 smtp.qq.com

登录邮箱->设置->账户->SMTP服务



开启POP3/SMTP服务

POP3/IMAP/SMTP/Exchange/CardDAV/CalDAV服务

开启服务： POP3/SMTP服务 (如何使用 Foxmail 等软件收发邮件?) 已关闭 | **开启**
IMAP/SMTP服务 (什么是 IMAP, 它又是如何设置?) 已关闭 | 开启
Exchange服务 (什么是Exchange, 它又是如何设置?) 已关闭 | 开启
CardDAV/CalDAV服务 (什么是CardDAV/CalDAV, 它又是如何设置?) 已开启 | 关闭
(POP3/IMAP/SMTP/CardDAV/CalDAV服务均支持SSL连接。如何设置?)

温馨提示：登录第三方客户端时，密码框请输入“授权码”进行验证(？)。生成授权码

开启成功：

The screenshot shows the 'POP3/IMAP/SMTP/Exchange/CardDAV/CalDAV服务' settings page. A dialog box titled '开启POP3/SMTP' is open, displaying the generated authorization code 'xtxh bpfv avpx dggg' in a red dashed box. A red arrow points to this code with the label '授权码'. Below the code, a red box highlights a tip: '提示：你可拥有多个授权码，所以无需记住该授权码，也不要告诉其他人。' with a '了解更多' link. The dialog also shows a table with account details: 名称: Mail team, 电子邮件: mailteam@qq.com, 密码: masked, 描述: Mail Team. The '确定' button is at the bottom right of the dialog. In the background settings page, the 'POP3/SMTP服务' status is now '已开启 | 关闭', with a red arrow pointing to '已开启'. The '生成授权码' button is also highlighted with a red box and a red arrow pointing to it with the label '可多次生成授权码'.

新浪邮箱SMTP服务

SMTP服务器 smtp.sina.com

登录邮箱->设置区->客户端pop/imap/smtp->POP3/SMTP服务状态开启->保存

- 常规设置
- 邮件签名
- 新邮件提醒
- 来信规则
- 分类管理
- 反垃圾设置
- 帐户中心
- 实验室
- 客户端pop/imap/smtp**
- 代收邮箱
- 手机服务
- 换肤
- 导航页签设置

POP3/SMTP服务

服务状态: 开启 关闭

收取时间: 收取自2016年12月15日以来的所有邮件 [收取全部](#) [更改时间](#)

客户端设置: POP3服务器: pop.sina.com

SMTP服务器: smtp.sina.com

(您可以使用Outlook,Foxmail等客户端软件来收发邮件。 [如何设置POP服务?](#))

收取范围: 收件夹 收件夹+归档邮件(移动到系统分类和自定义分类中的邮件)

同步选项: 禁止收信软件删除邮件

IMAP4服务/SMTP服务

服务状态: 开启 关闭

客户端设置: IMAP服务器: imap.sina.com

SMTP服务器: smtp.sina.com

(您可以使用Outlook,Foxmail等客户端软件来收发邮件。 [如何设置IMAP服务?](#))

保存 取消